

RANGER Client Guide

Notes: Remote PC users will only be able to connect if the machine is powered on. Ranger will attempt to wake the machine if offline but to be safe please always leave your machine on if you want to connect remotely.

Step 1: Open Internet Browser and go to <u>https://clientacronym</u>-ranger.datatechcloud.com</u>. If you do not have the correct URL please contact <u>support@datatechitp.com</u>.

	Download Client
Log in to RANGER	
user@domain	
Password	
Login	
Welcome to R.A.N.G.E.R	





KEEPING AN EYE ON YOUR TECHNOLOGY

Step2: Download the client & install on your machine.

Login to PANCED	
Log III to KANGER user@domain Password Login Welcome to R.A.N.G.E.R	
Download Parallels Client	
Download, install and configure the Parallels Client on your computer for better performance. Supported operating systems	
Installation process:	
Normality Norm	
Download Open the Parallels Client's setup and follow the onscreen instructions to install Configure	

To manually configure connection to the Parallels RAS, use the following settings:

Server:

datatechcloud.com

Port: 443 Connection Mode: Gateway SSL Mode

Support Portal | O365 Webmail | O365 Portal © 2019 Parallels International GmbH. All rights reserved.

Corporate: 7904 Hopi Place, Tampa FL, 33634 Phone: 800-473-1537, Fax: 813-872-1800 sales@lietzdev.com - www.datatechitp.com



Scorpion Interactive is an exclusive service of Lietz Development, Inc. 1996. All Rights Reserved.



KEEPING AN EYE ON YOUR TECHNOLOGY

Step 3: Run the client installation & follow the on-screen prompts.





REEPING AN EYE ON YOUR TECH	INOLOGY					
😽 Parallels Client-64 b	it Setup			_		>
End-User License	Agreement				Paral	lets
Please read the follo	owing license agreeme	nt carefully				J
Parallels End-	User License A	greemen	t			^
THIS END-USE "AGREEMENT" EITHER AN INE BELOW), AND ("PARALLELS"	ER LICENSE AG ") IS A LEGAL C DIVIDUAL OR AN PARALLELS IN) AND ITS AFFIL	REEMENT ONTRACT I ENTITY (TERNATIC IATES AN	(THIS BETWEE AS DEFIN NAL GME D SUBSID	en yc Ed H	ou, as	
READ THE TE CAREFULLY B OTHERWISE	RMS AND CONI EFORE COPYII ACCESSING OF	DITIONS C NG, INSTA USING P	OF THIS AG LLING, OF ARALLELS	GREE	MENT	*
☑ I accept the terms	s in the License Agreer	ment				
		$\overline{}$				
	Print	Back	Next		Car	icel
Parallels Client-64 b	it Setup			_		>
Parallels Client-64 b Destination Folde Click Next to install	it Setup r to the default folder o	r dick Change	to choose and		Paral	
Parallels Client-64 b Destination Folde Click Next to install Install Parallels Client	it Setup r to the default folder o -64 bit to:	r dick Change	to choose and			
Parallels Client-64 b Destination Folde Click Next to install Install Parallels Client C:\Program Files\Par	vit Setup r to the default folder o -64 bit to: rallels\Client\	r dick Change	to choose and	other.	(Para)
Parallels Client-64 b Destination Folde Click Next to install Install Parallels Client C:\Program Files\Par Change	rit Setup r to the default folder o -64 bit to: rallels\Client\	r dick Change	to choose and	other.	Para	;
 Parallels Client-64 b Destination Folder Click Next to install Install Parallels Client C:\Program Files\Par Change 	vit Setup f to the default folder o -64 bit to: rallels\Client\	r dick Change	to choose and	other.	Para	
Parallels Client-64 b Destination Folde Click Next to install Install Parallels Client C:\Program Files\Par Change	r to the default folder o -64 bit to: rallels\Client\	r dick Change	to choose and	other.	Para	;
Parallels Client-64 b Destination Folde Click Next to install Install Parallels Client C:\Program Files\Par Change	it Setup r to the default folder o -64 bit to: rallels\Client\	r dick Change	to choose and	other.	IIPara	;
 Parallels Client-64 b Destination Folde Click Next to install Install Parallels Client C:\Program Files\Par Change 	it Setup r to the default folder o -64 bit to: rallels\Client\	r dick Change	to choose and	other.	IIPara	;
 Parallels Client-64 b Destination Folde Click Next to install Install Parallels Client C:\Program Files\Par Change 	it Setup r to the default folder o -64 bit to: rallels\Client\	r dick Change	to choose and	other.	IPara	;]









Step 4: Configure the client connection.

Parallels Client		_	\times
File Applications Sessions Tools View Help			
$\leftarrow \rightarrow \uparrow$	3	Search	
Connections Info			
Parallels Client You have no RAS Connection configured, wo add one now? Yes	uld you like to		
0 items			E 🖩





KEEPING AN EYE ON YOUR TECHNOLOGY

Enter the server address, this will be the same as the web portal address.

Server: clientacronym-ranger.datatechcloud.com

New Connection	/	?		×
	Parallels®			
Server:	ranger.datatechcloud.com			
Connection mode:	Gateway SSL Mode			\sim
Friendly name:				
Advanced settings >			ОК	\supset

Once you click OK enter your user credentials (same as your workstation) & click connect.

🗊 Logon - 👘 ranger.datatechcloud.com			
	Parallels"		
Authentication Type:	Credentials ~		
<u>U</u> ser Name: Pass <u>w</u> ord:	dtech		
(Connect Cancel Options >>		

After connecting you will an icon for your office PC. These icons will also automatically be created on your desktop. Double clicking them will connect you to the respective desktops.

🗸 🏪 Connections	Info		
ranger.datatechcloud.com	Alberto	Candace	David Desktop
	Desktop	Desktop	David Desktop
	-	88	
	Jason Desktop	Jon Desktop	Justin Desktop

